

Ship to Size.....Min/Max Weeks set up

This new function will allow you to set up min/max weeks based on the size of the ship to.

1. AR Configuration Ship to Sizes set up.

The screenshot shows the 'A/R Configuration' window with the 'Ship-To Sizes' tab selected. On the left, there is a list of 'Ship-To Size Groups' with columns for group letter, description, and a ratio. Group 'A. Small' is selected. On the right, the 'Size Description' is 'Small', and the 'Minimum Weeks' is set to 0 and 'Maximum Weeks' is set to 1. At the bottom, there are 'Save' and 'Exit' buttons.

Group	Description	Ratio
A.	Small	0/1
B.	Medium	1/2
C.	large	3/4
D.	extra large	4/6
E.	<no description>	0/0
F.	<no description>	0/0
G.	<no description>	0/0
H.	<no description>	0/0
I.	<no description>	0/0
J.	<no description>	0/0

2. Client Maintenance, Ship to Maintenance, Misc tab Choose the Ship to Size that applies.

The screenshot shows the 'Client Maintenance' window, 'Misc' tab. It displays client information: 'Ship ID: GOLDF' and 'Description: MYERS HARDWARE CO. GOLDFIELD'. Under 'User Defined Fields', there are four fields, with the first containing 'REGION 1'. Below that, 'Consultant Set' is set to '<client default>', 'Link to Ship-To:' is empty, 'Ship-To Size:' is set to 'C (large)', and 'Alias ID:' is 'Alias ID Field'. 'Save' and 'Cancel' buttons are at the bottom.

3. Client Overrides allow you to change the ship to size definitions by client. These are found by editing the client. Go to program, Override Defaults, Ship to Sizes tab.

The screenshot shows the 'Client Override' window, 'Ship-To Sizes' tab. It features the same 'Ship-To Size Groups' list as the first screenshot, with 'A. Small' selected. On the right, the 'Override Default Sizes' checkbox is checked. The 'Size Description' is 'Small', and the 'Minimum Weeks' is set to 0. At the bottom, there are 'Save' and 'Cancel' buttons.

- Inventory Maintenance, Client Location/Usage allows you to override the ship to size by cost center/item.

Location Inventory

Client ID: MYHAR MYERS HARDWARE
 Item ID: ACC-050 INVOICE
 Loc ID: GOLDF MYERS HARDWARE CO. GOLDFIELD

Inventory Usage

Quantity Dollars UNIT: BX/100

Begin: 3,768.000 537,071.15 Date Last Inv: 02/11/2004
 Rcvd: 199,993.020 17,998,731.70
 End: 203,761.020 18,535,802.85 Location Memo: OFFICE 0
 Used: 0.000 Location Remarks: OFFICE

On Order: 200,000.000

Backordered: 0.000

Average Usage: 9.167

Average Price: 90.96835

Edit Location Inventory

Last Inventory: \$ Value
 Quantity: 3,768.000 537,071.15

Current Period:
 Quantity: 3,768.000 \$ Value
 Received: 199,993.020 17,998,731.70

TOTAL: 203,761.020 18,535,802.85
 Average Unit Price: 4,919.26827

Loc Memo: OFFICE 0
 Loc Remarks: OFFICE
 Last Inv Date: 02/11/2004

Override CC size settings
 Weeks: 2 5

*Unit = BX/100

Save Exit

- If you have previously set up min/max weeks on an item level, the highest minimum level will take preference, unless that is higher than the maximum allowed for the ship to. For Maximum weeks, if the ship to is zero or larger than the items maximum, the Items Maximum will take preference. Simply put e-Quantum will pull the largest available minimum and the smallest available maximum to fill the order.